




Backyard Roses Sleepover Set Tutorial


✧ Fabric Requirements & Pillow Case Cutting ✧



- 1 Yard Backyard Squares Blue
- 1 - 20" x 33" for the pillow back
- 2 - 5" x 20" strips for the pillow front
- 1 - 4" x 20" strip for the pillow front



- 1 Fat Quarter Backyard Stripe Orange
- 2 - 2" x 20" for the pillow front



- $\frac{3}{4}$ Yard Backyard Bouquet Green
- 1 - 11 $\frac{3}{4}$ " x 20" for the pillow front
- 1 - 1 $\frac{1}{4}$ " x 20" for the pillow front
- 3 - 2 $\frac{1}{4}$ " x WOF for the binding




- 1 - 22" x 38" panel of solid fabric for the pillow top backing
- 1 - 22" x 38" piece of cotton batting


✧ Pillow Case Assembly ✧

All seams are $\frac{1}{4}$ " unless otherwise noted.


1 Sew strips together as shown to make a 20" x 28" panel for the pillow front. Layer the backing, batting and top then quilt as desired.




2 Turn a $\frac{1}{4}$ " hem twice at one end of the back piece so that the raw edges are hidden. Stitch in place. Fold and then press the pillow back as shown so that it measures 20" x 27 $\frac{1}{4}$ " ($\frac{1}{4}$ " shorter than the front).



3 Layer the pillow back right side down and then the pillow top right side up. Make sure that the pillow back is $\frac{1}{4}$ " shorter than the top at the folded end. Baste $\frac{1}{8}$ " around both long sides and the short end without the fold.




4 Make and attach the binding using your favourite method. Pay careful attention at the folded/open end of the pillow to make sure that you don't accidentally catch the pillow back.




✕ Tote Bag Fabric Requirements & Cutting ✕



From the remaining Backyard Squares Blue
 2 - 11" x 14" for the bag lining
 2 - 4½" x 14" strips for the outside of the bag



From the remaining Backyard Bouquet Green
 2 - 1" x 8¼" for the outside of the bag
 2 - 4" x 17" for the bag handles



1 Fat Quarter Backyard Stripe Orange
 2 - 2¼" x 11" for the outside of the bag




Fusible interfacing/ShapeFlex 101
 2 - 11" x 14" pieces for the outside of the bag
 2 - 4" x 17" strips for the bag handles

✕ Tote Bag Assembly ✕


1 Fuse the ShapeFlex 101 to the wrong side of the bag handle strips. Press in half and then open up the strip and press the raw edges towards the centre. Stitch ⅛" from the open side to secure in place. Make 2.




2 Arrange and sew the outside bag panels as shown then fuse one of the 11" x 14" Shapeflex pieces to the wrong side of the panel. Measure 3" in from each side and pin the handle in place. Stitch ⅛" from the top to secure in place. Make 2.



3 Sew one of the 11" x 14" bag lining pieces to the bottom of an outside panel as shown. Make 2.



4 Place the completed bag panels together so that right sides are facing. Sew around each side leaving a 3" gap at the bottom of the bag.



5 Carefully lay out each corner of the bag and place on a cutting mat. Measure 2" from the corner and mark a line. Sew along the line and then trim as shown. Turn the bag right side out through the 3" opening, topstitch to close and press.

